ModusToolbox 101

Software Version: 2.3

Python




Software Installation Instructions

Before attending the ModusToolbox 101 training class, download and install the following software.

Python is required for both ModusToolbox and Mbed. For Windows, ModusToolbox will install the version that it uses. For MacOS and Linux, Python is often preinstalled on the system. If not, you will install a copy for ModusToolbox and Mbed to use. Note: Python 3.7.7. has been tested with the class material. Newer versions may work but they may not have been tested. Before installing, open a terminal window and enter python —version to see what is already installed.
<pre>MacOS: You will need to install Homebrew first to allow Python 3 to be installed (if it is not already present). https://brew.sh Once that is installed, just run brew install python3</pre>
Linux : Install python3 using your distribution's package manager (if it is not already present - it is usually installed by default). For example, on Ubuntu it is sudo apt install python3
ModusToolbox Software Download the software from this website: https://www.cypress.com/products/modustoolbox-software-environment See instructions at http://www.cypress.com/ModusToolboxInstallGuide
Visual Studio Code
Download the software from this website: https://code.visualstudio.com/
See instructions at https://code.visualstudio.com/docs/setup/setup-overview Once VS Code is installed, open it and install the C/C++ and Cortex Debug extensions:







CySmart

Install the CySmart application for Android or iOS to your mobile phone from the appropriate app store.